

Starting and Stopping the HTTP server

To Start HTTP server:

Type the following on a command line and then prompt.

```
Work with Active Jobs S10E9B6C 02/01/12 16:06:46
CPU %: 2.4 Elapsed time: 00:01:05 Active jobs: 383

Type options, press Enter.
 2=Change 3=Hold 4=End 5=Work with 6=Release 7=Display message
 8=Work with spooled files 13=Disconnect ...

Current
Opt Subsystem/Job User Type CPU % Function Status
--- KMAIL QSYS SBS .0 DEQW
--- QBATCH QSYS SBS .0 DEQW
--- QCMN QSYS SBS .0 DEQW
--- QCTL QSYS SBS .0 DEQW
--- QSYSSCD QPGMR BCH .0 PGM-QEZSCNEP EVTW
--- QHTTPSVR QSYS SBS .0 DEQW
--- ADMIN QTMHHTTP BCH .0 PGM-QZHBMAIN SIGW
--- ADMIN QTMHHTTP BCI .0 PGM-QZSRLOG SIGW
--- ADMIN QTMHHTTP BCH .0 PGM-QLWISVR JVAW
More...

Parameters or command
==> STRTCPSVR █

F3=Exit F5=Refresh F7=Find F10=Restart statistics
F11=Display elapsed data F12=Cancel F23=More options F24=More keys

MA A MW 21/017
```

And then fill in as shown...

```
Start TCP/IP Server (STRTCPSVR)

Type choices, press Enter.

Server application . . . . . > *HTTP      *ALL, *AUTOSTART...
      + for more values
Restart server . . . . . *NONE      *NONE, *HTTP, *DNS, *DHCP...
HTTP server:
  Server instance . . . . . *admin    Name, *ALL, *ADMIN
  Instance startup values . . .

Bottom
F3=Exit  F4=Prompt  F5=Refresh  F12=Cancel  F13=How to use this display
F24=More keys
```

Now enter.

To end HTTP server—

Type ENDTCPSVR and prompt. Then fill in as shown: enter *http and then enter to get the instance field presented.

End TCP/IP Server (ENDTCPSVR)

Type choices, press Enter.

Server application > *HTTP _____ *ALL...
+ for more values _____
HTTP server:
Server instance *admin|_____ Name, *ALL, *ADMIN

Bottom

F3=Exit F4=Prompt F5=Refresh F12=Cancel F13=How to use this display
F24=More keys

Enter.